

Slurm: A quick start tutorial

Slurm is a resource manager and job scheduler. Users can submit jobs (i.e. scripts containing execution instructions) to slurm so that it can schedule their execution and allocate the appropriate resources (CPU, RAM, etc..) on the basis of a user's preferences or the limits imposed by the system administrators. Clearly, the advantages of using slurm on a computational cluster are multiple. For an overview of them please read [these pages](#).

Slurm is **free** software distributed under the [GNU General Public License](#).

What is a parallel job?

A parallel job consists of tasks that run simultaneously. Parallelization can be achieved in different ways, among which:

- by running a multi-process program, for example using [OpenMPI](#).
- by running a multi-threaded program, for example see [pthreads](#).

A multi-process program consists of multiple tasks orchestrated by MPI and possibly executed by different nodes. On the other hand, a multi-threaded program consists of multiple task using several CPUs on the same node.

Slurm's command ``srun'` (see below) allows users to create tasks and/or request CPUs for a particular task such that both types of parallelizations mentioned above can be achieved easily. For instance, the `-ntasks n (-N)` option will create **n processes**, while the `-cpus-per-task n (-c)` option will create a single **n-threaded process**. Tasks cannot be split across several compute nodes. See the examples below.

Slurm's architecture

Slurm is made of a `slurmd` daemon running on each compute node and a central `slurmctld` daemon running on a management node (with the possibility of setting up a fail-over twin). If ``accounting'` is enabled, then there is a third daemon called `slurmdbd` managing the communications between an accounting database and the management node.

Common slurm user commands include `sacct`, `salloc`, `sattach`, `sbatch`, `sbcast`, `scancel`, `scontrol`, `sinfo`, `smap`, `squeue`, `srun`, `strigger` and `sview` and they are available on each compute node. Manual pages for each of these commands are accessible in the usual manner, that is `man sbatch` for example (see below).

Node

A node in slurm is a compute resource. This is usually defined by particular consumable resources, i.e. memory, CPU, etc...

Partitions

A partition (or queue) is a set of nodes with usually common characteristics and/or limits.

Partitions group nodes into logical (even overlapping if necessary) sets.

Jobs

Jobs are allocations of consumable resources assigned to a user under specified conditions.

Job Steps

A job step is a single task within a job. Each job can have multiple tasks (steps) even parallel ones.

Common user commands

- **sacct**: used to report job or job step accounting information about active or completed jobs.
- **salloc**: used to allocate resources for a job in real time. Typically this is used to allocate resources and spawn a shell. The shell is then used to execute srun commands to launch parallel tasks.
- **sbatch**: used to submit a job script for later execution. The script typically contains an srun command to launch parallel tasks plus any other environment definitions needed.
- **scancel**: used to cancel a pending or running job or job step.
- **sinfo**: used to report the state of partitions and nodes managed by Slurm.
- **squeue**: used to report the state of running and pending jobs or job steps.
- **srun**: used to submit a job for execution or initiate job steps in real time. srun allows users to requests arbitrary consumable resources.

Examples

Determine what partitions exist on the system, what nodes they include, and the general system state.

```
$ sinfo
PARTITION AVAIL  TIMELIMIT  NODES  STATE NODELIST
playground* up    infinite    4  alloc maris[029-032]
playground* up    infinite   32  idle  maris[004-022,033,035-046]
lowmem     up  7-00:00:00    1  mix  maris047
lowmem     up  7-00:00:00   20  idle  maris[048-050,052-068]
lowmem-inf up    infinite    1  mix  maris047
lowmem-inf up    infinite   20  idle  maris[048-050,052-068]
highmem    up  7-00:00:00    6  idle  maris[069-074]
highmem-inf up    infinite    6  idle  maris[069-074]
notebook   up    infinite    2  mix  maris[023-024]
notebook   up    infinite    4  idle  maris[025-028]
```

A * near a partition name indicates the default partition. See man sinfo

What jobs exist on the system?

```
$squeue
```

	JOBID	PARTITION	NAME	USER	ST	TIME	NODES	
NODELIST(REASON)								
	12277	lowmem	CFnumder	marxxxel	R	1:23:18	1	maris047
	12276	playgroun	pkequal_	maxxxxel	R	1:24:57	1	maris032
	8439	notebook	obrien-j	oxxxen	R	18:10:55	1	maris024
	8749	playgroun	slurm_co	oxxxxxkh	R	17:28:55	1	maris029
	5801	notebook	ostroukh	oxxxxxkh	R	4-05:02:54	1	maris023
	8750	playgroun	slurm_en	oxxxxxkh	R	17:28:52	4	

maris[029-032]

See man squeue.

Report more detailed information about partitions, nodes, jobs, job steps, and configuration

```
$ scontrol show partition notebook
PartitionName=notebook
  AllowGroups=ALL AllowAccounts=ALL AllowQos=ALL
  AllocNodes=ALL Default=NO QoS=notebook
  DefaultTime=NONE DisableRootJobs=NO ExclusiveUser=NO GraceTime=0
Hidden=NO
  MaxNodes=UNLIMITED MaxTime=UNLIMITED MinNodes=1 LLN=NO
MaxCPUsPerNode=UNLIMITED
  Nodes=maris0[23-28]
  PriorityJobFactor=1 PriorityTier=1 RootOnly=NO ReqResv=NO
OverSubscribe=NO
  OverTimeLimit=NONE PreemptMode=OFF
  State=UP TotalCPUs=48 TotalNodes=6 SelectTypeParameters=NONE
  DefMemPerNode=UNLIMITED MaxMemPerCPU=4096
```

```
$scontrol show node maris004
NodeName=maris004 Arch=x86_64 CoresPerSocket=4
  CPUAlloc=8 CPUErr=0 CPUTot=8 CPULoad=0.01
  AvailableFeatures=(null)
  ActiveFeatures=(null)
  Gres=(null)
  NodeAddr=maris004 NodeHostName=maris004 Version=16.05
  OS=Linux RealMemory=16046 AllocMem=16000 FreeMem=2082 Sockets=2 Boards=1
  State=ALLOCATED ThreadsPerCore=1 TmpDisk=9951 Weight=1 Owner=N/A
MCS_label=N/A
  BootTime=2016-12-22T12:08:05 SlurmdStartTime=2017-02-17T09:19:46
  CapWatts=n/a
  CurrentWatts=0 LowestJoules=0 ConsumedJoules=0
  ExtSensorsJoules=n/s ExtSensorsWatts=0 ExtSensorsTemp=n/s
```

```
novamaris [1087] $ scontrol show jobs 1052
JobId=1052 JobName=slurm_engine.sbatch
  UserId=xxxxxxx(1261909) GroupId=lorentz(9999) MCS_label=N/A
  Priority=1 Nice=0 Account=zzzzzz QOS=normal
  JobState=RUNNING Reason=None Dependency=(null)
  Requeue=1 Restarts=0 BatchFlag=1 Reboot=0 ExitCode=0:0
  RunTime=00:49:06 TimeLimit=UNLIMITED TimeMin=N/A
  SubmitTime=2017-02-23T12:17:34 EligibleTime=2017-02-23T12:17:34
  StartTime=2017-02-23T12:17:36 EndTime=Unknown Deadline=N/A
  PreemptTime=None SuspendTime=None SecsPreSuspend=0
  Partition=average-computation AllocNode:Sid=maris004:20658
  ReqNodeList=(null) ExcNodeList=(null)
  NodeList=maris[024-033,035-040]
  BatchHost=maris024
  NumNodes=16 NumCPUs=128 NumTasks=128 CPUs/Task=1 ReqB:S:C:T=0:0:*:*
  TRES=cpu=128,mem=514784M,node=16
  Socks/Node=* NtasksPerN:B:S:C=0:0:*:* CoreSpec=*
  MinCPUsNode=1 MinMemoryNode=32174M MinTmpDiskNode=0
  Features=(null) Gres=(null) Reservation=(null)
  OverSubscribe=OK Contiguous=0 Licenses=(null) Network=(null)
  Command=./slurm_engine.sbatch
  WorkDir=/marisdata/%u/
  StdErr=/marisdata/xxxxxxx/.log/abcd.err
  StdIn=/dev/null
  StdOut=/marisdata/xxxxxxx/.log/abcd.out
  Power=
```

See man `scontrol`.

Create three tasks running on different nodes

```
novamaris [1088] $ srun -N3 -l /bin/hostname
2: maris007
0: maris005
1: maris006
```

Create three tasks running on the same node

```
novamaris [1090] $ srun -n3 -l /bin/hostname
2: maris005
1: maris005
0: maris005
```

Create three tasks running on different nodes specifying which nodes should at least be used

```
srun -N3 -w "maris00[5-6]" -l /bin/hostname
1: maris006
0: maris005
2: maris007
```

Allocate resources and spawn job steps within that allocation

```
novamaris [1094] $ salloc -n2
salloc: Granted job allocation 1061
novamaris [997] $ srun /bin/hostname
maris005
maris005
novamaris [998] $ exit
exit
salloc: Relinquishing job allocation 1061
novamaris [1095] $
```

Create a job script and submit it to slurm for execution



Use `swizard` to generate a batch script.

Or wrote your own script to submit using `sbatch script.sh`.

Less-common user commands

- **sacctmgr**
- **sstat**
- **sshare**
- **sprio**

sacctmgr

Display info on configured qos

```
$ sacctmgr show qos format=Name,MaxCpusPerUser,MaxJobsPerUser,Flags
      Name MaxCPUsPU MaxJobsPU              Flags
-----
   normal
playground      32          1          DenyOnLimit
  notebook      4           1          DenyOnLimit
```

sstat

Displays information pertaining to CPU, Task, Node, Resident Set Size (RSS) and Virtual Memory (VM) of a running job

```
$sstat -o JobID,MaxRSS,AveRSS,MaxPages,AvePages,AveCPU,MaxDiskRead
8749.batch

      JobID      MaxRSS      AveRSS MaxPages      AvePages      AveCPU
```

MaxDiskRead

--						
8749.batch	196448K	196448K	0	0	01:00.000	7.03M



If your job is serial (not parallel, that is not submitted using `srun`) do not forget to append `.batch` to the job id.



For parallel jobs `sstat <jobid>` will work.

sshare

Display the shares associated to a particular user

```
$ sshare -U -u xxxxx
```

Account	User	RawShares	NormShares	RawUsage
xxxxx	yyyyyy	1	0.055556	691078

EffectvUsage FairShare

0.005142 0.937857



On maris, usage parameters will decay over time according to a `PriorityDecayHalfLife` of 14 days.

sprio

Display priority information of a pending job id xxx

```
sprio -l -j xxx
```

Tips

To minimize the time your job spends in the queue you could specify multiple partitions so that the job can start as soon as possible. Use `--partition=notebook,playground,lowmem`

To have a rough estimate of when your queued job will start type `squeue --start`

To translate a job script written for a scheduler different than slurm to slurm's own syntax consider using <http://www.schedmd.com/slurmdocs/rosetta.pdf>

top-like node usage

Should you want to monitor the usage of the cluster nodes in a top-like fashion type

```
watch -n 1 -x sinfo -S"-0" -o "%.9n %.6t %.10e/%m %.100 %.15C"
```

top-like job stats

To monitor the resources consumed by your running job type

```
watch -n1 sstat --format  
JobID,NTasks,nodelist,MaxRSS,MaxVMSize,AveRSS,AveVMSize,AveCpuFreq  
<jobid>[.batch]
```

Make local file available to all nodes allocated to a slurm job

To transmit a file to all nodes allocated to the currently active Slurm job use sbcast. For instance

```
> cat my.job  
#!/bin/env bash  
sbcast my.prog /tmp/my.prog  
srun /tmp/my.prog  
  
> sbatch --nodes=8 my.job  
srun: jobid 145 submitted
```

Specify nodes for a job

For instance `#SBATCH --nodelist=maris0xx`

Environment variables available to any slurm job

You can use any of the following variables in your jobs

```
$ salloc -p playground -N 10  
salloc: Granted job allocation 13709  
$ printenv | grep -i slurm_  
SLURM_NODELIST=maris[031-033,035-041]  
SLURM_JOB_NAME=bash  
SLURM_NODE_ALIASES=(null)  
SLURM_JOB_QOS=normal  
SLURM_NNODES=10  
SLURM_JOBID=13709  
SLURM_TASKS_PER_NODE=1(x10)
```

```
SLURM_JOB_ID=13709
SLURM_SUBMIT_DIR=/tmp/bla-bla
SLURM_JOB_NODELIST=maris[031-033,035-041]
SLURM_CLUSTER_NAME=maris
SLURM_JOB_CPUS_PER_NODE=1(x10)
SLURM_SUBMIT_HOST=novamaris.lorentz.leidenuniv.nl
SLURM_JOB_PARTITION=playground
SLURM_JOB_ACCOUNT=yuyuysu
SLURM_JOB_NUM_NODES=10
SLURM_MEM_PER_NODE=32174
```

From:

<https://helpdesk.physics.leidenuniv.nl/wiki/> - **Computer Documentation Wiki**

Permanent link:

https://helpdesk.physics.leidenuniv.nl/wiki/doku.php?id=slurm_tutorial&rev=1491900494

Last update: **2017/04/11 08:48**

